BOUNCER User Guide


Version 1.1.15

When a registered person appears on the camera, BOUNCER **instantly hides the windows you chose and mutes them.** It can also bring another window to the front. Press `F9` once to bring everything back. Face recognition runs only on this PC.

1 Getting started

1. Double-click the BOUNCER file (e.g. `BOUNCER_v1.1.15.exe`). No installation.
   If "Windows protected your PC" appears: **More info** → **Run anyway**.
2. Choose your **language** (한국어/English) the first time.
3. On a new PC the first start takes **1–2 minutes** of setup. Please wait (later starts take about 10 seconds).


2 The main window



1	**Camera view**	6	**Watched people** — registered people (double-click for their photos)
2	**Status · time left today**	7	**Hide** — windows to hide
3	**Watch / Stop** (`F9`)	8	**Kill hidden programs** (`F12`)
4	**Settings** (gear)	9	**Show** — window to bring to the front
5	**New faces** — unknown faces seen by the camera		

3 Adding people

- **From New faces** — when the person passes the camera, their face appears in **New faces**. Click it and press **Add**. It's added right away (named "Person 1", … automatically).
- **From a photo** — press **Photo** under **Watched people** and choose a face photo.
- **Learns by itself** — each time a watched person is clearly recognised, BOUNCER keeps photos from new angles (up to 10 per person). The list shows the most frontal, sharpest one.
- **View / delete recognition photos** — **double-click** a person's photo. If someone else got in, select that photo and press **Delete**.
- **Remove a person** — click the photo, press **Delete** → **Yes**.



Recognition photos (double-click a person)

4 Windows to hide and show

1. Open the program you want to hide.
2. Pick its window in the **Hide** drop-down and press **+**. (To remove: select it in the list and press **-**.)
3. (Optional) pick a window to show instead under **Show** and press **+**.

● = open now, ○ = not open right now. A window is hidden if its **title contains the text** — browser titles change with each tab, so use the program name such as `Chrome` or `Edge`.

5 Watching

Key	Action
F9	**Watching on / off.** Turning it off brings back all hidden windows and their sound.
F12	**Kill hidden programs** (only while watching). Unsaved work is lost and F9 can't bring them back.

While watching, when a registered person is seen, **the hidden windows disappear and are muted**, and the Show window comes to the front. Hiding a browser mutes the whole browser. Hotkeys work even when the BOUNCER window isn't visible.

6 Tray

- **X** doesn't quit — it moves BOUNCER to the **tray** (next to the clock), where it keeps watching.
- Tray icon: **green** watching / **red** stopped. **Hover** to see the time left today.
- **Double-click** = open. **Right-click** = Open / Watch / Donate / **Quit**.

7 Settings (gear)

Source	Which camera. Restart BOUNCER after changing it.
Match threshold	Higher = stricter (fewer wrong triggers), lower = catches more. Change in steps of 0.02–0.05. Default 0.45
FPS	Set automatically. Lower it if the PC lags.
Min face px	Faces smaller (farther) than this are ignored. Default 50
Language	한국어 / English. Applies after restart.

8 Usage period and donation

Period	Use	Title · time left
First 15 days (trial)	No time limit · ad popup once an hour	BOUNCER - Trial (n days left) · **Unlimited**
After 15 days (free)	**8 hours** a day (only counts while watching, renewed at midnight KST) · ad popup	BOUNCER - Free · from **8:00:00**
After donating	**Unlimited** on that PC · no ads	BOUNCER · **Unlimited**

Donate with TRON (Settings or tray menu → **Donate**):

1. The window shows a **deposit address for this PC** with a QR code.
2. Send **TRX** on the TRON network to that address — **10 TRX or more** is needed (scan the QR or **Copy address**).
3. Within 1–2 minutes this PC becomes **unlimited** automatically.



The address shown is an example

9 If something's wrong

Black camera view	Check that no other program (Zoom, Teams) is using the camera and that Settings → Privacy & security → Camera allows desktop apps.
Registered person not detected	Check that watching is ON and the Hide list shows ●. It improves after a few more sightings; otherwise lower the threshold slightly.
Reacts to the wrong person	Double-click that person and delete photos of someone else; otherwise raise the threshold slightly.
Hidden window doesn't come back	Press `F9`. Quitting BOUNCER also restores them. (Programs closed with F12 must be started again.)
Nothing happens on double-click	BOUNCER is already in the tray — double-click the tray icon.

When asking for help, send the version (in Settings) and the file `%LOCALAPPDATA%\화면보호\화면보호.log`.